

Festo PARTdataManager

Instructions for manual Deployment / network installation

The Deployment option in the installer copies the selected features to specified folders for manual deployment to one or more PCs. Administrators can use it to provide Festo PARTdataManager to multiple users via a network share.

The Deployment option does not install Festo PARTdataManager on the local PC. No Start Menu shortcuts or Registry entries are created.

Administrative privileges are required to perform the deployment step, not to use Festo PARTdataManager.


Please note that Festo CAD-Plugins are not supported with manually deployed Festo PARTdataManager.

Preparing Deployment

Run the installer file
Festo_offline_12.11.1.248524.msi and
disable the "Simple installation" option to
enable selection of destination folders.
You can specify local paths or UNC paths as
destination folders.

Activate the "Deployment" option.


Note: Festo PARTdataManager will not be
installed; only files will be copied to the
specified folders.



FESTO

Disable CAD-Plugins

Deactivate all „Integrations“ and the feature „Activate interfaces on client“, as CAD-Plugins are not supported with manually deployed Festo PARTdataManager.




Adjusting start.env

If the deployed files are moved to a different location after Festo PARTdataManager Setup is finished, the start.env file in the software folder must be updated manually.

Relative paths can be used by referencing variables defined within *start.env*.

For example:

`CADENAS_DATA=$CADENAS\..\data`



Sample start.env with relative paths

Copy following content to start.env

[ENVIRONS]

CADENAS=%DirOfThisFile%

CADENAS_SETUP=\$CADENAS\..\setup

CADENAS_DEFAULTUSER=\$CADENAS_SETUP\user\default_user

CADENAS_SITESETUP=\$CADENAS\..\sitesetup

CADENAS_USER=%UserAppData%\Festo PARTdataManager\user

CADENAS_LICENSE=\$CADENAS_SITESETUP\lic

CADENAS_POOL=\$CADENAS\..\pool

CADENAS_DATA=\$CADENAS\..\data

Using Festo PARTdataManager

QuickSearchPlus can be used to select products and start Festo PARTdataManager.

<https://www.festo.com/quicksearch>

You can select the path to Festo PARTdataManager in QuickSearchPlus.

Alternatively users can run Festo PARTdataManager directly starting:

`..\bin\x86\64\pdatamgr.exe`