

Release Notes | QuickSearchPlus 2025-02



[Working Offline](#)



[Offline Config](#)



[2D/3D CAD](#)

Offline Operating Instructions

Copy [OperatingInstructions.CAT](#)

Festo FTP Server: https://ftp.festo.com/Public/PNEUMATIC/SOFTWARE_SERVICE/QuickSearch/OperatingInstructions/

next to your [QuickSearchPlus.exe](#)

The screenshot displays the QuickSearchPlus software interface. At the top, the product details for '1501330 Safety module CAMC-G-S1' are shown, including a shipping date, price (BASISPREIS 10520), and a 'Deliver!' button. A 3D model of the module is visible on the right. Below the product details is a search bar containing 'CAMC-G-S1'. A toolbar with various icons is present, and a red arrow points to the 'Operating instruct.' icon. The main area shows a list of products, with 'CAMC-G-S1' selected. An 'Operating instruct.' dialog box is open, showing a list of documents for the selected part. The dialog box has a language dropdown set to 'English [3]'. The list includes:

Part Number	Description	Document Type
8035903 - CAMC-DS-/CAMC-G-...-D2	Safety module	Assembly instructions
8219420 - CAMC-G-S1-EN	Safety module	Manual
8219410 - CAMC-G-S1-DE	Safety module	Brief instruction

At the bottom of the dialog box, there are buttons for 'Show PDF' and 'Show Online', and a 'Close' button.

Release Notes | QuickSearchPlus 2024-12



[Working Offline](#)



[Offline Config](#)



[2D/3D CAD](#)

2 new country/language combinations EN-DE and EN-CH

..added at the end of the selection box



For your convenience, put country/language switch to F-Function key

> Motors and servo drives

> Industrial robots

> Vacuum technologies

> Valves and valve terminals

> Sensors

> Compressed air preparation

> Tubes, fittings, plugs and cables

> Control technology and remote I/O

> Function-specific systems

> Other pneumatic components

> Software

> Pneumatic grippers



> Motion Terminal

- F1** Options.. > EN - English CH ▶
- F2** Options.. > FR - Français CH ▶
- F3** Options.. > DE - Deutsch CH ▶
- F4** Action on function key F4 ▶
- F5** Action on function key F5 ▶
- F6** Action on function key F6 ▶
- F7** Action on function key F7 ▶
- F8** Action on function key F8 ▶
- F9** Action on function key F9 ▶
- F10** Action on function key F10 ▶
- F11** Action on function key F11 ▶
- F12** Action on function key F12 ▶


EN

Bring QS+ Window to front if product found on the clipboard

Either focused or unfocused



Focus stays in your App to **continue working there**



Focus jumps to QuickSearchPlus to **continue working there**

Show warning if product found on clipboard is phased-out

..use in combination with bring window to front

> Motion Terminal



- ✓ Clipboard monitoring on/off
 - If a product is found on clipboard.. >
 - Show.. >
 - Copy to clipboard.. >
- ✓ Make the window flash
 - Bring Window to front (focused)
 - Bring Window to front (un-focused)
- ✓ Show MessageBox when Phased-Out

Phased-out - click here for alternatives


ADN-12-25-I-P-A-C

Type ^	NEW R LT ▲ L	Part no.	Designation
ADN-12-10-A-P-A-C	◆	8076022	Compact cylinder
ADN-12-10-I-P-A-C	◆	8075943	Compact cylinder
ADN-12-15-A-P-A-C	◆	8075934	Compact cylinder
ADN-12-15-I-P-A-C	◆	8075944	Compact cylinder
ADN-12-20-A-P-A-C	◆	8075935	Compact cylinder
ADN-12-20-I-P-A-C	◆	8075945	Compact cylinder
ADN-12-25-A-P-A-C	◆	8075936	Compact cylinder
ADN-12-25-I-P-A-C	◆	8075946	Compact cylinder
ADN-12-30-A-P-A-C	◆	8075937	Compact cylinder
ADN-12-30-I-P-A-C	◆	8075947	Compact cylinder
ADN-12-35-A-P-A-C	◆	8075938	Compact cylinder
ADN-12-35-I-P-A-C	◆	8075948	Compact cylinder
ADN-12-40-A-P-A-C	◆	8075939	Compact cylinder
ADN-12-40-I-P-A-C	◆	8075949	Compact cylinder
ADN-12-50-A-P-A-C	◆	8075940	Compact cylinder
ADN-12-50-I-P-A-C	◆	8075950	Compact cylinder

Phased-out products


⚠ Phased-out products
Compact cylinder 8075946 ADN-12-25-I-P-A-C

OK



Bugs Fixes


Download local Picture **NOW** function back to normal



Link to Engineering tool Pneumatic Simulation changed to <https://www.festo.com/us/en/x/pneumatic-simulation/>

Fixed the **links to catalog in Excel export**

1	537712	SOEG-E-M
1	537701	SOEG-RT
1	537702	SOEG-RT
1	537693	SOEG-S-M
1	537698	SOEG-RS
1	537714	SOEG-RS



Parts list **icon spacing** extended



Re-order of items in parts list much faster now

Release Notes | QuickSearchPlus 2024-10



- 68 phased-out part numbers
- + 130 new part numbers



[Working Offline](#)






[Offline Config](#)



[2D/3D CAD](#)

Limited width of the product picture and symbol arrangement

No more jumping of text and pictures in the upper left corner, pneumatic symbol vertically centered



Adjust with in **Options** to fit your preference

Accessories level with grey line

Type ^	NEW R LT ▲ L ◆ ★	Part no.	Designation	PU
▼ VMEF-ST-M32-M-G14	▲ ◆ ★	8031300	Stem actuated valve	1
> Recommended Accessories				
▼ Push-in fittings				
← QS-G1/4-10-I	◆ ★	186112	Push-in fitting	10
▼ Tubing				
> PAN		553610	Plastic tubing	1
▼ PAN-10X1,5-BL		553909	Plastic tubing	50
> Recommended Accessories				
▼ General accessories				
PB-140		6741	Tubing strap	10
PB-172		6742	Tubing strap	10
← PB-378		6743	Tubing strap	10
PKB-50-BL		3656	Spiral wrap for tubing	50
▼ ZRS	◆	7658	Pipe and tubing cutter	1
▼ General accessories				
← ZRS 10PACK.	◆	218606	Blade	1
> PAN-10X1,5-BL-300		553897	Plastic tubing	300
> PAN-10X1,5-GE		553933	Plastic tubing	50
> PAN-10X1,5-GN		553921	Plastic tubing	50
> PAN-10X1,5-NT		546287	Plastic tubing	50

1st level

2nd level

3rd level

4th level

·
·
·
·

The Return of the electric symbols

I have found a new source for the **electric symbols**. Will go into **clipboard** and **Excel** export!

5251373 Motor cable
NEBM-M23G15-EH-12-Q7N-R3LEG14
 Shipping date [United Kingdom]
 Stroke length 0.5...99m
 Electrical connection 1, connection ty... Hybrid socket
 Electrical connection 1, connector sys... M23x1
 Electrical connection 2, connection ty... Plugs and cables
 Electrical connection 2, connector sys... RJ45 and open en
 Cable length 0.5 ... 100 m

NEBM-M23G15-EH-12-Q7N-R3LEG14

Type ^	PU
NEBM-M17G12-EH-10-Q6N-LE12	1
NEBM-M17G12-EH-10-Q7N-LE12	1
NEBM-M23/40	1
NEBM-M23G15-EH- -Q10N-R3LEG14	1
NEBM-M23G15-EH- -Q7N-R3LEG14	1
NEBM-M23G15-EH- -Q0N-R3LEG14	1

8097196 Adapter
NEFM-REG6-K-0.5-B-REG6
 Shipping date [United Kingdom]

8097196

Type ^	Part	PU
> NEDY-L2R1-V1-Z4W2Z-U-0.3L-M8G4-2.5R		1
> NEDY-L2R1-V1-Z4W2Z-U-0.3L-M8G4-5R		1
NEFC-M12G5-0.3-U1G5		1
NEFC-M12G8-0.3-M12G5-LK		1
NEFC-S1G25-C2W25-S6		1
> NEFC-S1G25-C2W25-S7		1
NEFF-S1G44LB		1
NEFM-REG6-K-0.5-B-R3G8	8097195	1
NEFM-REG6-K-0.5-B-REG6	8097196	1

8181677 Motor cable
NEBM-L10G14-EH-2.5-Q6N-LE12
 Shipping date [United Kingdom]


Electrical connection 1, connection t... Hybrid socket
 Electrical connection 1, connector s... Plug pattern L10
 Electrical connection 2, connection t... Cable
 Electrical connection 2, connector s... Open en
 Cable length 2.5 m

8181677



Type ^	PU
NEBM-H7G2-E-2U-Q14N-LE2	1
NEBM-H7G2-E-25-Q14N-LE2	1
NEBM-H7G2-E-5-Q14N-LE2	1
NEBM-H7G2-E-7.5-Q14N-LE2	1
NEBM-L10G14-EH-2.5-Q6N-LE12	1

Consolidate

With this new feature you can choose to consolidate same products in parts list **only if packaging unit is >1**



Quantity	Part no.	Type	Designation	ID1
10			Blanking plug	B-1/8
10	3568	B-1/8	Blanking plug	B-1/8
50	159664	PUN-6X1-BL	Plastic tubing	PUN-6X1-BL
50	159664	PUN-6X1-BL	Plastic tubing	PUN-6X1-BL
1	2225	O-3/8	Sealing ring	O-3/8
1	2225	O-3/8	Sealing ring	O-3/8







Quantity	Part no.	Type	Designation	ID1
20	3568	B-1/8	Blanking plug	B-1/8
100	159664	PUN-6X1-BL	Plastic tubing	PUN-6X1-BL
1	2225	O-3/8	Sealing ring	O-3/8
1	2225	O-3/8	Sealing ring	O-3/8

Without this option, these 2 would have been consolidated either

Good to know – core range stars by country

Make sure you have set your country correct, because the star is **individual per country**

Article	Belgium
 Mini-chariot ★ DGST-16-125-PA 8085137 <input type="checkbox"/> Comparer	
 Mini-chariot DGST-16- - 8073895 <input type="checkbox"/> Comparer	
 Mini-chariot DGST-16-125-E1A 8078860 <input type="checkbox"/> Comparer	
 Mini-chariot DGST-16-125-Y12A 8085181 <input type="checkbox"/> Comparer	

Article	Canada
 Mini-chariot ★ DGST-16-125-E1A 8078860 <input type="checkbox"/> Comparer	
 Mini-chariot ★ DGST-16-125-PA 8085137 <input type="checkbox"/> Comparer	
 Mini-chariot ★ DGST-16-125-Y12A 8085181 <input type="checkbox"/> Comparer	
 Mini-chariot DGST-16- -	

Article	Australia
 Mini slide ★ DGST-16- - 8073895 <input type="checkbox"/> Compare	
 Mini slide ★ DGST-16-125-E1A 8078860 <input type="checkbox"/> Compare	
 Mini slide ★ DGST-16-125-PA 8085137 <input type="checkbox"/> Compare	
 Mini slide ★ DGST-16-125-Y12A 8085181 <input type="checkbox"/> Compare	



Bugs Fixes and Minor Improvements

Short description

Fixed link to FDT-Online in **Engineering Tools** menu

Accessories loaded from within QuickSearchPlus.exe and no more from Online (faster and more reliable)

Empty lines in **photo export to Excel** – Festo IT fixed the issue

Click on **symbol to zoom**, click **again to un-zoom**

Release Notes | QuickSearchPlus 2024-07



Offline Configuration | No Internet – No Problem

The image shows two overlapping windows of the Festo configurator. The top window is titled '530906 - DGC-8- - Linear drive' and has a green checkmark and 'Online FESTO' logo. The bottom window is titled '530906 - DGC-8- - Linear drive' and has a red 'X' and 'Offline FESTO' logo. Both windows show a hierarchical tree on the left with categories like 'Actuators', 'Motors and servo drives', and 'Industrial robots'. The main area displays a parts list table with columns for 'Part no.', 'Designation', 'Type', 'ID1', and 'ID2'. A red arrow points to the 'Configure' button in the top window, and another red arrow points to the 'IC Check' button in the bottom window. A third red arrow points to the 'Quick Add' button in the bottom window.

Part no.	Designation	Type	ID1	ID2
8089687	Stopper cylinder			
8089691	Stopper cylinder			
8089686	Stopper cylinder			
8089690	Stopper cylinder			
8089685	Stopper cylinder			
8089689	Stopper cylinder			
530906	Linear drive			
530907	Linear drive			
532446	Linear drive			
567547	Linear drive			
532447	Linear drive			
567548	Linear drive			

Offline functions

- Check configuration
- Open configurator
- Live ID code check while typing
- ID code detection on clipboard
- Quick-Add to parts list
- IC Check in parts list


Limitations while offline

- No product key e.g. 3S7PLBL10CK
- No OrderID e.g. C475540
- No Accessories
- No price, no delivery time, no SAP,..

But works if button is pressed “accidentally”

Offline Configuration | How to copy ... Unzip .. start

1. Copy latest **Configurator_2024_MM_DD.zip** from https://ftp.festo.com/Public/PNEUMATIC/SOFTWARE_SERVICE/QuickSearch/
2. Unzip **Configurator_2024_MM_DD.zip** below **QuickSearchPlus.exe**
3. Your QS+ directory should look like this



Note:

No **special characters** in the path name allowed.

No **OneDrive** or **Network Drive** allowed.

QS+ and Online Catalog | Consolidated Tree Nodes

- Products 2024.05
- Industrial automation**
- > Actuators
- > Motors and servo drives
- > Industrial robots
- > Vacuum technologies
- > Valves and valve terminals
- > Sensors
- > Compressed air preparation
- > Tubes, fittings, plugs and cables
- > Control technology and remote I/O
- > Function-specific systems
- > Other pneumatic components
- > Software
- > Pneumatic grippers
- > Motion Terminal
- > Ready-to-install solutions
- > Services
- Process automation**
- > Control technology and remote I/O
- > Valve terminals
- > NAMUR valves
- > Limit switch attachments
- > Valve positioners
- > Drives
- > Process and media valves
- > Air preparation
- > Pneumatic connection technology
- > Services

- Products 2024.07
- > Actuators
- > Motors and servo drives
- > Industrial robots
- > Vacuum technologies
- > Valves and valve terminals
- > Sensors
- > Compressed air preparation
- > Tubes, fittings, plugs and cables
- > Control technology and remote I/O
- > Function-specific systems
- > Other pneumatic components
- > Software
- > Pneumatic grippers
- > Motion Terminal
- > Ready-to-install solutions
- > Services

Automation Didactic Automation Didactic



Products Solutions Support Technical education Products Solutions Support Technical education

> Products

- Industrial automation**
Products for automation in manufacturing and assembly
- Process automation
Products for handling liquids and bulk materials
- LifeTech automation
Products for laboratory devices and medical devices

For easier navigation, all Festo products are now sorted into one single product tree

New Button | Link to Online Catalog Tree Nodes from QS+ Tree Nodes



Adjust no. of products in parts list to **packaging units**

Quantity -> Packaging Unit

Quantity	Part no.	Type	Designation	ID1	PU
25	553889	PAN-6X1-SI-500	Plastic tubing	PAN-6X1-SI-500	500
50	569885	PEN-3/8-SW-150-CB	Plastic tubing	PEN-3/8-SW-150-CB	150
250	130712	QSF-1/4-6-B-100	Push-in fitting	QSF-1/4-6-B-100	100
25	153084	QSLL-3/8-12	Push-in L-fitting, long	QSLL-3/8-12	10
8	153066	QSL-6HL	Push-in L-connector	QSL-6HL	10
66	8025714	VFFG-T-M5-12	Flow control	VFFG-T-M5-12	10
22	8025714	VFFG-T-M5-12	Flow control	VFFG-T-M5-12	10

Before

Quantity	Part no.	Type	Designation	ID1	PU
500	553889	PAN-6X1-SI-500	Plastic tubing	PAN-6X1-SI-500	500
150	569885	PEN-3/8-SW-150-CB	Plastic tubing	PEN-3/8-SW-150-CB	150
300	130712	QSF-1/4-6-B-100	Push-in fitting	QSF-1/4-6-B-100	100
30	153084	QSLL-3/8-12	Push-in L-fitting, long	QSLL-3/8-12	10
10	153066	QSL-6HL	Push-in L-connector	QSL-6HL	10
70	8025714	VFFG-T-M5-12	Flow control	VFFG-T-M5-12	10
30	8025714	VFFG-T-M5-12	Flow control	VFFG-T-M5-12	10

After


One click for **correct packaging unit** size, especially after QuickAdd to parts list

Also remember the **Consolidate same items** Feature.

Quantity	Part no.	Type	Designation
23	8025714	VFFG-T-M5-12	Flow control
11	8025714	VFFG-T-M5-12	Flow control




Quantity	Part no.	Type	Designation
34	8025714	VFFG-T-M5-12	Flow control



Engineering Tools Menu | Restructured

So far, new tools are were added at the end of menu.

With the new structure, tools are **grouped by technology**



Special

EA

EA

Others



Bugs Fixes and Minor Improvements

Short description

After language/country change, the **shown product information will be translated**

The wrong code **QS-1/2-10** was accidentally routed to **QS-12-10** due to over-engineered algorithm 😊

SGS-M16*1.5 is now recognized as **SGS-M16X1,5** on clipboard and QuickAdd to parts list

**NEBM-M23G15-EH-25-Q9N-R3LEG14 is not routed to
NEBM-M23G15-EH-2.5-Q9N-R3LEG14 now (FEHA vs. x-LENGTH)**

QuickAdd to clipboard: a mixture of type/ID and part number are now converted correctly

Identcode check in parts list with progress dialog and **Cancel** option

The screenshot shows a SAP interface with a parts list table and an 'IC Check' dialog box. The dialog box displays 'IC Check' and '5/16', with a 'Cancel' button. A red box highlights the 'IC Check' button in the bottom right corner of the SAP window.

Quantity	Part no.	Type	Designation	ID1	ID2
1	18200	CPV10-VI	Valve terminal	10P-10-4A-MP-R-C-CP3L-EX1E-UL1+ZHA-E	
1	197330	CPX	Terminal	50E-F23GCQS-Z	
1	532307	MSB6N	Service unit combination	MSB6N-AQS:09:09:09:09:09:09:09:09	
1	539105	MPA-MPM-VI	Valve terminal	32E-MPM+E	32P-SGL-RMBB-4J
1	539215	VTSA-MP	Valve terminal	44E-MP1-B-L-CN	44P-R-X-KX-FFSUEEA
1	539218	VTSA-FB-NPT	Valve terminal		44PN-N-V-ABC-OJKG
1	539506	CPV10-EX-VI	Manifold assembly		45P-R-X1-KX-BBU4C
1	547963	VTSA-F-MP	Valve terminal		50E-F33GCQPXDGV
1	552938	MSB9	Service unit combination		
1	569926	MPAC-VI	Valve terminal		
1	572230	VTUG-S	Manifold assembly		
1	573606	VTUG	Valve terminal		
1	575465	MPAC-VI	Valve terminal		
1	577304	VTUS-20	Manifold assembly	VTUS-20-SC1F7-1H2L-GD-Q10TB-4G+HCL4	
1	8022016	VTUS-25	Manifold assembly	VTUS-25-SC1F8-1DZ-Q16L-GD-Q10TB-4G+HCL4	
1	8042554	VUVG	Solenoid valve	VUVG-BK10-T32C-AT-F-1H2L-S	

FESTO

Quick Search Plus
Version 2024-05



Copyright © Festo AG & Co. KG

QuickSearchPlus

2024-05

Release Notes

Insert item above selected item in parts list

The screenshot shows a software interface with a parts list table. A context menu is open over the selected row. The 'Insert' option is highlighted, and a new item is being added above the selected row.

Quantity	Part ...	Type	Designation	Str...	Re..
1	175...	GRLA-M3	One-way flow cont...		
1	187...	MPPES-3-1/4-...	Proportional-pres...		
1	13989	PZVT-99999-...	Timer		

The screenshot shows the same software interface after the new item has been inserted. The new item is now at the top of the parts list, above the previously selected item.

Quantity	Part no.	Type	Designation	I
1	175038	GRLA-M3	One-way flow control valve	G
1	30649	S-3-BE-SW	Micro switch	S
1	187333	MPPES-3-1/4-10-010	Proportional-pressure r...tor	M
1	13989	PZVT-99999-MIN-B	Timer	P

Insert items above selected item in parts list

3

Valves Ins

Insert

30648 S-3-BEMicro switch

30649 S-3-BE-SWMicro switch

7843 S-3-PK-3-BMicro stem actuated valve

above

30649 S-3-BE-SW Micro switch

S in parts list > Valves<

> S-3-BE-SW

> S-3-PK-3-B

SACC-FH-G-S3

> SACC-N8-SP

SACC-PN-G

Part no. Designation

4031 Swivel lever valve

52432 Roller lever valve

9694 Pneumatic limit val...

30648 Micro switch

30649 Micro switch

7843 Micro stem actuate...

8069031 Protective hood

8184143 Impact protection

8035560 Protective hood

2

Xiaoli Test[4] Valves[3] XLength Missing[10] Parts list 4[6] Parts list 5[0]

Quantity	Part no.	Type	Designation	ID1
1	175038	GRLA-M3	One-way flow control valve	GR
1	30649	S-3-BE-SW	Micro switch	S-
1	13989	PZVT-99999-MIN-B	Timer	PZ

1

- 1 Select a line in the parts list
- 2 Choose **new items** (hold down Shift or CTRL)
- 3 Click the **Insert .. above** button
- 4 The **new items** added **above** the selected line

Xiaoli Test[4] Valves[6] XLength Missing[10] Parts list 4[6] Parts list 5[0]




Quantity	Part no.	Type	Designation	ID1
1	175038	GRLA-M3	One-way flow control valve	GR
1	30648	S-3-BE	Micro switch	S-3
1	30649	S-3-BE-SW	Micro switch	S-3
1	7843	S-3-PK-3-B	Micro stem actuated valve	S-3
1	30649	S-3-BE-SW	Micro switch	S-3
1	13989	PZVT-99999-MIN-B	Timer	PZ

4

New selection to view catalog PDF – **Show PDF in Acrobat** and no **Dxxx.PDF** name anymore

PDFs in Browser are shown with a Dxxxx.PDF file name.

With the new setting **Save to Downloads Folder and Show** the documents are downloaded first and opened in Acrobat



Positioning of pictures and symbols in Excel export improved (reported by Jurgen)























	Photo	Quanti	Part no.	ID1
1		4	8082408	ELCC-TB-KF-90-2000-0H
2		2	5255537	EMMT-AS-100-L-HS
3		4	8081061	DASI-E21-90/110-S
4		4	8081060	DASI-E21-90-S8-C
5		4	8067062	DAYP-E21-90
6		2	8082459	DHAA-R-E21-70...110-F
7		4	160274	YSR-32-60-C
8		8	150391	SIEN-M8B-PO-S
9		4	556815	EGC-120-2000-TB-KF-2024-02
10		24	558044	MUE-120/185

	Photo	Quanti	Part no.	ID1	Designation
1		4	8082408	ELCC-TB-KF-90-2000-0H-P0-CR	Cantilever axis
2		2			Motor
3		8			ch lug
4		4			or bracket
5		4			k absorber
6		2			k absorber
7		4			proximity sens
8		8			head belt a
9		4			EGC-120-2000-TB-KF-2024-02
10		24			MUE-120/185
11		2	555539	EMMT-AS-100-M-HS-RMB	Servo motor
12		8	551392	SIES-8M-PO-24V-K-0,3-M8D	Proximity sens





bugs fixes and minor improvements

Short description

VTUC-EX configurator start without error message

Right-click copy on part no/type/description for C-codes now shows C-code

Valid KMAT codes shown as incorrect e.g. DSNU-32-60-PPS-A

DFM-12-...-B (529119) and DFM-16-...-B (529120) show a x-length, not as configurable products

Action “CAD on Function key” not working

Picture quality in Outlook mail are not as good as in 2023-11 version

FESTO

Quick Search Plus
Version 2024-01



Copyright © Festo AG & Co. KG

QuickSearchPlus

2024-01

Release Notes

Replace selected item in parts list

The screenshot shows the software interface with the 'Replace' button highlighted by a black box with the number '3'. A dropdown menu is open, showing a list of replacement items. The first item in the list is '157244 AEVUZ-80-10-P-A Compact air cylinder', which is highlighted by a blue arrow and a black box with the number '2'. The 'Replace' button is also highlighted by a black box with the number '1'.

Quantity	Part no.	Type	Designation	ID1
1	549194	AKM-12	Cover cap	AKM-12
1	10399	AH-06-B	Toggle lever	AH-06-B
1	157246	AEVUZ-80-20-P-A	Compact air cylinder	AEVUZ-80-20-P-A
1	157306	FLA-80	Flange mounting	FLA-80

- 1 Select a line in the parts list
- 2 Choose the **new item** in the product list
- 3 Click the **Replace** button
- 4 The line is replaced by the **new item**

The screenshot shows the software interface with the updated parts list. The 'Replace' button is highlighted by a black box with the number '4'. The 'Compact air cylinder' line has been replaced by '157244 AEVUZ-80-10-P-A Compact air cylinder'.

Quantity	Part no.	Type	Designation	ID1
1	549194	AKM-12	Cover cap	AKM-12
1	10399	AH-06-B	Toggle lever	AH-06-B
1	157244	AEVUZ-80-10-P-A	Compact air cylinder	AEVUZ-80-10-P-A
1	157306	FLA-80	Flange mounting	FLA-80

Insert item after selected item in parts list

1

3

Insert

Type	Part no.	Designation
> AEVUZ-157244	AEVUZ-80-10-P-A	Compact air cylinder
> AEVUZ-157248	AEVUZ-100-10-P-A	Compact air cylinder
> AEVUZ-157249	AEVUZ-100-15-P-A	Compact air cylinder
> AEVUZ-157294	AEVUZ-100-10-A-P-A	Compact air cylinder
> AEVUZ-157248	AEVUZ-100-10-P-A	Compact air cylinder
> AEVUZ-157295	AEVUZ-100-15-A-P-A	Compact air cylinder
> AEVUZ-157249	AEVUZ-100-15-P-A	Compact air cylinder
> AEVUZ-157296	AEVUZ-100-20-A-P-A	Compact air cylinder

2

Quantity	Part no.	Type	Designation	ID1
1	549194	AKM-12	Cover cap	AKM-12
1	10399	AH-06-B	Toggle lever	AH-06-B
1	157244	AEVUZ-80-10-P-A	Compact air cylinder	AEVUZ-80-10-P-A
1	157248	AEVUZ-100-10-P-A	Compact air cylinder	AEVUZ-100-10-P-A
1	157306	FUA-80	Flange mounting	FUA-80

1

- 1 Select a line in the parts list
- 2 Choose the **new item** in the product list
- 3 Click the **Insert** button
- 4 The **new item** is added **after** the selected line

4

Quantity	Part no.	Type	Designation	ID1
1	549194	AKM-12	Cover cap	AKM-12
1	10399	AH-06-B	Toggle lever	AH-06-B
1	157244	AEVUZ-80-10-P-A	Compact air cylinder	AEVUZ-80-10-P-A
1	157248	AEVUZ-100-10-P-A	Compact air cylinder	AEVUZ-100-10-P-A
1	157306	FUA-80	Flange mounting	FUA-80

Insert items after selected item in parts list

The screenshot shows the software interface with the 'Insert' button highlighted by a black box with the number '3'. A dropdown menu is open, showing a list of parts. A blue arrow points to the 'Insert' button. Below the dropdown, a parts list is shown with a selected line (part 157244) and new items added after it. A black box with the number '1' is placed over the selected line. A blue arrow points to the 'Insert' button. A black box with the number '2' is placed over the new items added after the selected line. A blue arrow points to the 'Insert' button.

Quantity	Part no.	Type	Designation	ID1
1	549194	AKM-12	Cover cap	AKM-12
1	10399	AH-06-B	Toggle lever	AH-06-B
1	157244	AEVUZ-80-10-P-A	Compact air cylinder	AEVUZ-80-10-P-A
1	157306	FLIA-80	Flange mounting	FLIA-80

- 1 Select a line in the parts list
- 2 Choose **new item** (hold down Shift or CTRL)
- 3 Click the **Insert** button
- 4 The **new items** added **after** the selected line

The screenshot shows the software interface with the parts list updated. A black box with the number '4' is placed over the new items added after the selected line. A blue arrow points to the 'Insert' button.

Quantity	Part no.	Type	Designation	ID1
1	549194	AKM-12	Cover cap	AKM-12
1	10399	AH-06-B	Toggle lever	AH-06-B
1	157244	AEVUZ-80-10-P-A	Compact air cylinder	AEVUZ-80-10-P-A
1	157248	AEVUZ-100-10-P-A	Compact air cylinder	AEVUZ-100-10-P-A
1	157249	AEVUZ-100-15-P-A	Compact air cylinder	AEVUZ-100-15-P-A
1	157250	AEVUZ-100-20-P-A	Compact air cylinder	AEVUZ-100-20-P-A
1	157306	FLIA-80	Flange mounting	FLIA-80

Online product data and QuickSearch product data are identical now

Home > Products > Industrial automation > Tubes, fittings, plugs and cables > Pneumatic connection technology > Pneumatic fittings > Barbed fittings > CK > ACK-1/8-PK-6

Online

Quick connector

ACK-1/8-PK-6
7842
GTIN: 4052568020231

Pneumatic connection, port 1	Female thread G1/8
Pneumatic connection, port 2	For tubing outside diameter of 8 mm - For barbed fitting inside diameter of 6 mm with nut
Ambient temperature	-10 °C - 60 °C

Product tree

- Industrial automation
 - Actuators
 - Motors and servo drives
 - Industrial robots
 - Vacuum technologies
 - Valves and valve technology
 - Sensors
 - Machine vision
 - Compressed air preparation
- Tubes, fittings, plugs and cables
 - Electrical connection technology
 - Pneumatic connection technology
 - Pneumatic tubing
 - Pneumatic fittings
 - Push-in fittings
 - Barbed fittings
 - Quick connector CK**
 - Barbed fitting CN
 - Barbed hose fitting C-P N-P
 - Fitting NPCK

Top features

Pneumatic connection, port 1	Female thread G1/8
Pneumatic connection, port 2	For tubing outside diameter of 8 mm For barbed fitting inside diameter of 6 mm with nut
Ambient temperature	-10 ... 60 °C

QuickSearch (QS+)

7842 **Quick connector**

Shipping date UVP/RRP 81403 → Deliver!

Type	Part no.	Designation	PU
> ACK-1/4-PK-6	3712	Quick connector	10
> ACK-1/8-PK-3	5664	Quick connector	10
> ACK-1/8-PK-4	3714	Quick connector	10
> ACK-1/8-PK-6	7842	Quick connector	10

New Thai and Vietnamese
Removed Russian, Latvian, Lithuanian

All accessories and recommended accessories like online catalog

The image displays a user interface for an online catalog, divided into two main sections: 'Recommended accessories' and 'All accessories'.

Recommended accessories section:

- Filter by: Only recommended Accessories
- Product list items:
 - DLAG KF 25 150 PPSA (5072371) Linear actuator
 - DADG 1L N8 P2 (8069000) Cable holder
 - DAMH-L8-25-P-1 (8069000) Profile mounting
 - DAYP-L8-25 (8069000) Shock absorber ...
 - DYSS-8-8-Y1F (8069002) Pneumatic choc...
 - GRLA-1/8-QS-6-D (★ 193144) One-way flow c...
 - QS-G1/8-6 (★ 186096) Push-in fitting
 - QS-G1/8-6-I (★ 186107) Push-in fitting
 - QSL-G1/8-6 (★ 186117) Push-in L-fitting
 - SDBT-MSX-1L-NU-E-0.3-N-M8 (★ 8059123) Proximity sensor
 - SDBT-MSX-1L-NU-E-2.5-N-LE (★ 8059124) Proximity sensor
 - SDBT-MSX-1L-PU-E-0.3-N-M8 (★ 8059120) Proximity sensor
 - SDBT-MSX-1L-PU-E-2.5-N-LE (★ 8059121) Proximity sensor
 - SMT-8M-A-NS-24V-E-0.3-M8D (★ 574339) Proximity sensor
 - SMT-8M-A-NS-24V-E-2.5-OE (★ 574338) Proximity sensor
 - SMT-8M-A-PS-24V-E-0.3-M8D (★ 574334) Proximity sensor
 - SMT-8M-A-PS-24V-E-2.5-OE (★ 574335) Proximity sensor
 - VFOE-LE-T-G18-Q6 (★ 8068726) One-way flow c...

All accessories section:

- Filter by: All Accessories
- Product list items:
 - Mounting accessories
 - Cylinder sensors for direct mounting
 - Function fittings
 - Other connectors
 - Barbed fittings
 - Quick connectors
 - Push-in fittings

Blue arrows indicate the flow of information: 'Recommended accessories' points to the 'Recommended Accessories' dropdown in the product list, and 'All accessories' points to the expanded list of accessory categories in the 'All Accessories' section.

Product Name	Part Number	Description
DLAG KF 25 150 PPSA	5072371	Linear actuator
DADG 1L N8 P2	8069000	Cable holder
DAMH-L8-25-P-1	8069000	Profile mounting
DAYP-L8-25	8069000	Shock absorber ...
DYSS-8-8-Y1F	8069002	Pneumatic choc...
GRLA-1/8-QS-6-D	★ 193144	One-way flow c...
QS-G1/8-6	★ 186096	Push-in fitting
QS-G1/8-6-I	★ 186107	Push-in fitting
QSL-G1/8-6	★ 186117	Push-in L-fitting
SDBT-MSX-1L-NU-E-0.3-N-M8	★ 8059123	Proximity sensor
SDBT-MSX-1L-NU-E-2.5-N-LE	★ 8059124	Proximity sensor
SDBT-MSX-1L-PU-E-0.3-N-M8	★ 8059120	Proximity sensor
SDBT-MSX-1L-PU-E-2.5-N-LE	★ 8059121	Proximity sensor
SMT-8M-A-NS-24V-E-0.3-M8D	★ 574339	Proximity sensor
SMT-8M-A-NS-24V-E-2.5-OE	★ 574338	Proximity sensor
SMT-8M-A-PS-24V-E-0.3-M8D	★ 574334	Proximity sensor
SMT-8M-A-PS-24V-E-2.5-OE	★ 574335	Proximity sensor
VFOE-LE-T-G18-Q6	★ 8068726	One-way flow c...

Takeover of **AdditionalInformation.txt** and **Filter.txt** information to **Fluiddraw**



8042559 - VUVG-BK10-M52-AT-F-1R8L-S Air solenoid valve Gewicht: 50 g (PK): 2.1.014 (ZA4) Zolltarifrnr.: 84812090 (DE) EUR 45,47

Close Product Finder Engineering New products History GTIN: 4052568286873 PL CE Kennzeichen: Copper-free: not Copper-free Kernprogramm: NO

ADREM INDUSTRIES

4 products selected

VUVG-BK10-M52-AT-F-1R8L-S	8042559	Air solenoid valve	50 g	84812090 (DE)
VUVG-BK10-T32C-AT-F-1H2L-S	8042554	Air solenoid valve	55 g	84812090 (DE)
VUVG-BK10-T32C-AT-F-1R8L-S	8042558	Air solenoid valve	55 g	84812090 (DE)
VUVG-BK14-B52-T-F-1H2L-S	8042572	Air solenoid valve	85 g	84812090 (DE)

Fluid draw Copy CAD Compare products Compare products Show Online

Type	Part no.	Designation	PU	Gewicht	PG (PK)	Zolltarifrnr.:	EUR	PL	GTIN:	CE Kennzeichen:	Copper-free:	Kernp
> VUVG	564212	Air solenoid valve	1	50 g	2.1.014 (ZA4)	84812090 (DE)	Konfi...			nach EU-EMV...	not Copper-free	
> VUVG-BK10-B52-T-F-1H2L-S	8042556	Air solenoid valve	1	57 g	2.1.014 (ZA4)							
> VUVG-BK10-B52-T-F-1R8L-S	8042560	Air solenoid valve	1	50 g	2.1.014 (ZA4)							
> VUVG-BK10-M52-AT-F-1H2L-S	8042555	Air solenoid valve	1	45 g	2.1.014 (ZA4)							
> VUVG-BK10-M52-AT-F-1R8L-S	8042559	Air solenoid valve	1	50 g	2.1.014 (ZA4)							
> VUVG-BK10-T32C-AT-F-1H2L-S	8042554	Air solenoid valve	1	55 g	2.1.014 (ZA4)							
> VUVG-BK10-T32C-AT-F-1R8L-S	8042558	Air solenoid valve	1	55 g	2.1.014 (ZA4)							
> VUVG-BK14-B52-T-F-1H2L-S	8042572	Air solenoid valve	1	85 g	2.1.014 (ZA4)							
> VUVG-BK14-B52-T-F-1R8L-S	8042576	Air solenoid valve	1	85 g	2.1.014 (ZA4)							

Insert Products from List


Menge	Teilenummer	Proc	Ker	Typ	Verpackung	Artikl	Meng	Bezeichn	Gewicht:	Zolltarifrnr.:	GTIN:	CE Kennzeichen:	Kernprogramm:	LABS haltige Stoffe enthalten	Auswahl
1	8042559			VUVG-BK10-M52-AT-F-...	1	Ma...	STK	VUV...	50 g	84812090 (DE)	4052568286873		NO	L	<input checked="" type="checkbox"/>
1	8042554			VUVG-BK10-T32C-AT-F-...	1	Ma...	STK	VUV...	55 g	84812090 (DE)	4052568286835		NO	L	<input checked="" type="checkbox"/>
1	8042558			VUVG-BK10-T32C-AT-F-...	1	Ma...	STK	VUV...	55 g	84812090 (DE)	4052568286866		NO	L	<input checked="" type="checkbox"/>
1	8042572			VUVG-BK14-B52-T-F-1...	1	Ma...	STK	VUV...	85 g	84812090 (DE)	4052568286972		NO	L	<input checked="" type="checkbox"/>

OK Cancel

Fluiddraw

VUVG-BK10-M52-AT-F-1R8L-S VUVG-BK10-T32C-AT-F-1H2L-S VUVG-BK10-T32C-AT-F-1R8L-S VUVG-BK14-B52-T-F-1H2L-S

lfd. Nr.	Stück	Kennzeichnung	Teilenummer	Typ	Artikelbenennung	Gewicht:	GTIN:	Zolltarifrnr.:
1	1	-QM2	8031518	VU VG-B14-T...	Magnetventil	80 g	405256828817	84812090 (DE)
2	1	-QM6	8042559	VUVG-BK10-...	Magnetventil	50 g	4052568286873	84812090 (DE)
3	1	-QM7	8042554	VU VG-BK10-...	Magnetventil	55 g	4052568286835	84812090 (DE)
4	1	-QM8	8042558	VU VG-BK10-...	Magnetventil	55 g	4052568286866	84812090 (DE)
5	1	-QM9	8042572	VUVG-BK14-...	Magnetventil	85 g	4052568286972	84812090 (DE)



Small product thumbnail as **photo** (no black and white line drawing like before)

Click this button to see

551456 plastic tubing **2023-11**

Shipping date \$UVP/RRP 81403 → Deliver!

PEN-4X0,75-BL


Type	Part no.	Designation	PU
PEN-4X0,75-BL	551456	plastic tubing	50
PEN-4X0,75-BL-500	551444	plastic tubing	500
PEN-4X0,75-GE	551480	plastic tubing	50
PEN-4X0,75-GN	551468	plastic tubing	50
PEN-4X0,75-NT	543246	plastic tubing	50
PEN-4X0,75-RT	551474	plastic tubing	50
PEN-4X0,75-SI	551462	plastic tubing	50
PEN-4X0,75-SI-500	551450	plastic tubing	500
PEN-4X0,75-SW	543240	plastic tubing	50
PEN-4X0,75-SW-500	551438	plastic tubing	500
PEN-6X1-BL	551457	plastic tubing	50
PEN-6X1-BL-500	551445	plastic tubing	500
PEN-6X1-GE	551481	plastic tubing	50
PEN-6X1-GN	551469	plastic tubing	50
PEN-6X1-NT	543247	plastic tubing	50
PEN-6X1-RT	551475	plastic tubing	50
PEN-6X1-SI	551463	plastic tubing	50
PEN-6X1-SI-500	551451	plastic tubing	500
PEN-6X1-SW	543241	plastic tubing	50
PEN-6X1-SW-500	551439	plastic tubing	500
PEN-8X1,25-BL	551458	plastic tubing	50
PEN-8X1,25-BL-400	551446	plastic tubing	400
PEN-8X1,25-GE	551482	plastic tubing	50
PEN-8X1,25-GN	551470	plastic tubing	50
PEN-8X1,25-NT	543248	plastic tubing	50

551456 Plastic tubing **2024-01**

Shipping date \$UVP/RRP 81403 → Deliver!

PEN-4X0,75-BL

Type	Part no.	Designation	PU
PEN-4X0,75-BL	551456	Plastic tubing	50
PEN-4X0,75-BL-500	551444	Plastic tubing	500
PEN-4X0,75-GE	551480	Plastic tubing	50
PEN-4X0,75-GN	551468	Plastic tubing	50
PEN-4X0,75-NT	543246	Plastic tubing	50
PEN-4X0,75-RT	551474	Plastic tubing	50
PEN-4X0,75-SI	551462	Plastic tubing	50
PEN-4X0,75-SI-500	551450	Plastic tubing	500
PEN-4X0,75-SW	543240	Plastic tubing	50
PEN-4X0,75-SW-500	551438	Plastic tubing	500
PEN-6X1-BL	551457	Plastic tubing	50
PEN-6X1-BL-500	551445	Plastic tubing	500
PEN-6X1-GE	551481	Plastic tubing	50
PEN-6X1-GN	551469	Plastic tubing	50
PEN-6X1-NT	543247	Plastic tubing	50
PEN-6X1-RT	551475	Plastic tubing	50
PEN-6X1-SI	551463	Plastic tubing	50
PEN-6X1-SI-500	551451	Plastic tubing	500
PEN-6X1-SW	543241	Plastic tubing	50
PEN-6X1-SW-500	551439	Plastic tubing	500
PEN-8X1,25-BL	551458	Plastic tubing	50
PEN-8X1,25-BL-400	551446	Plastic tubing	400
PEN-8X1,25-GE	551482	Plastic tubing	50
PEN-8X1,25-GN	551470	Plastic tubing	50
PEN-8X1,25-NT	543248	Plastic tubing	50



Button **What is new in version xxx**





bugs fixes and minor improvements

Short description

Fix column width when **copy parts list to Online-Outlook** in Browser

When moving mouse on tiny product thumbnail, product picture turned white

Removed unit conversion tool from internal SPIMS+ menu (tool no more available)

Fixed an issue with phased-out MS4- and MS6- products which are part of KMAT now